

Getting Started

SpotOn!™ Flexo 2.6

**All you need to know to get started,
every step of the way.**

- How to **install** the software
- How to **activate** the software
- How to **contact us**

Languages

SpotOn! is written in English. If we receive demand for other languages, we will certainly consider publishing localized versions of SpotOn!

Platform requirements

Windows Client minimum

Windows XP Pro SP3 or higher
Pentium 4 or higher
160GB Hard Drive
1GB RAM
1024x768 16-bit Color
1 USB ports

Macintosh Client minimum

OS 10.5.8 or higher
Intel
160GB Hard Drive
1GB RAM
1024x768 16-bit Color
1 USB ports

Windows Server minimum

Windows XP Pro SP3 or higher
Pentium 4 or higher
160GB Hard Drive
1GB RAM
1024x768 16-bit Color
1 USB ports

Table of Contents

Do you have a Demo version?	2
Measurement Instruments	2
Installation Steps for Windows Server.....	3
Server setup.....	4
Installation Steps for Windows Client	6
Installation Steps for Mac Client.....	7
Client login.....	8
Online Activation Steps.....	9
Offline Activation Steps	10
Contact Information	12

BEFORE YOU DO ANYTHING...

Follow the Installation Steps, then the Activation Steps, as explained.

Do you have a Demo version?

If you downloaded or were given a **Demo version**, the product will run for 30 days and then quit. You will need to purchase a product key to keep using SpotOn!. During the 30 day trial period the **Demo version** has full functionality. Please contact sales@spotonpress.com or your dealer to purchase the full version.

Measurement Instruments

Here is a list of instruments that work with SpotOn!:

X-Rite i1 Pro and Pro 2
X-Rite eXact (Windows only)
X-Rite 530
X-Rite 939
X-Rite SpectroEye
X-Rite SP62-64
Techkon SpectroDens (Windows only)
Konica-Minolta FD-7 (Windows Only)

INSTALLATION STEPS FOR WINDOWS SERVER


WINDOWS

Step 1: *Double-click* on the **SpotOnServer.exe** file to launch the installation wizard.

Step 2: Follow the steps in the wizard to install SpotOn! Server.



Step 3: Click *Finish*. **SpotOn! Server** is installed and running in the background as a service. The default administrative user is called **admin** with a password of **admin**. See the next section to set up more users.




SERVER SETUP


WINDOWS




Step 1: Click the **SpotOn! Admin** shortcut in the Start menu to launch the Server Admin application.



Step 2: The Server Admin application allows the user to turn the server service on or off. When installed, it is on by default. Click the red icon button to turn the server off.




Click the green arrow icon to turn the server on. The Server Admin application is also where additional users can be added and configured.




Note: The **Show Log...** button will open a window where the database and log files are stored, making it easy to find for backup purposes and troubleshooting.

Step 3: Click **Manage Users** to add, edit, or remove Users. The **Manage Users** window will appear where these administrative functions can be performed.




Step 4: Click **Add** to add a new User. The **Create New User** window will appear. Fill in the Username, Full name, and Password for the new user. Pick the **User Type**. An **Operator** can only access the Instruments section in Settings. An **Administrator** has full functionality.




The 'Create a New User' dialog box has a title bar 'Create a New User'. Inside, the title is 'Create a new user login'. It contains four text input fields: 'Username:', 'Full name:', 'Password:', and 'Re-enter Password:'. Below these is a 'User Type:' section with two radio buttons: 'Operator' (selected) and 'Administrator'. At the bottom are two buttons: 'Create User' and 'Cancel'.

Step 5: To edit a User, select the User in the list on the left and click **Edit**.




The 'Manage Users' dialog box has a title bar 'Manage Users' and sub-titles 'Ede' and 'Edit'. On the left is a table with columns 'Username' and 'Type'. It lists 'admin' (Administrator) and 'bruce' (Operator), with 'bruce' selected. On the right, the details for 'bruce' are shown: 'Username: bruce', 'Full name: Bruce Bayne', 'Password:' with a 'Reset' button, and 'User Type:' with 'Operator' selected. At the bottom are 'Add', 'Delete', 'Edit', and 'Cancel' buttons.

Step 6: Everything except the **Username** can be changed when editing a User. The only way to change a **Username** is to delete the User and add a new User with a different name. Click **Save** to save the User changes.



This 'Manage Users' dialog box is identical to the previous one, but the 'Save' button is visible at the bottom right instead of the 'Edit' button.

Step 7: To change the **Password**, click **Reset**. In the Change Password window create a new Password and re-enter it. Click **Change Password** to save the new Password for the User being edited.




The 'Change Password' dialog box has a title bar 'Change Password' and a title 'Reset user's password'. It contains three text input fields: 'Login name: bruce', 'New Password:', and 'Re-enter Password:'. At the bottom are two buttons: 'Change Password' and 'Cancel'.

CLIENT INSTALLATION STEPS FOR WINDOWS


WINDOWS

Step 1: *Double-click* on the **SpotOn.exe** file to launch the installation wizard.


Step 2: Follow the steps in the wizard to install SpotOn! Flexo. If any **Security Warning** windows appear *select* **Run** or **Install this driver software anyway** to continue with the installation wizard.



Step 3: *Read* the **License Agreement** carefully and if you accept the conditions of the agreement *click* the **I accept the agreement** radio button and *click* **Next >**.



Step 4: *Click* **Finish**. SpotOn! Flexo is installed and ready to use for 30 days, or purchase a **Product Key** to activate for unlimited use.




CLIENT INSTALLATION STEPS FOR MAC

MAC




Step 1: Double-click on the **SpotOn.dmg** file to mount the SpotOn! Flexo disk image.


Step 2: Read the **License Agreement** carefully and if you accept the conditions of the agreement click the **Agree** button.



Step 3: Drag the **SpotOn! Flexo** icon onto the Applications icon.



Step 4: Eject the **SpotOn!** disk image. SpotOn! Flexo is installed and ready to use for 30 days, or purchase a **Product Key** to activate for unlimited use.




CLIENT LOGIN



WINDOWS and MAC



Note: When the SpotOn! Client is launched for the first time a **Server Setup** window opens asking the user to choose between **Local Mode** and **SpotOn! Server Mode**. Choose the mode. This choice can be changed in the **General Settings** section once a setting has been chosen.



Step 1: When a User logs into a newly installed and registered SpotOn! Client for the first time, a blank **User Login** screen appears. Enter the **Server IP address** with **:13707** at the end, the **Username**, and **Password**. Click **Log In** to start using the Client. If **Server Mode** was accidentally chosen and there is no server installed, click the **Use local database...** button to switch back to **Local Mode**.



Note: In subsequent Logins, the User isn't required to re-enter the Server or Username, as SpotOn! remembers the previous Login. Only the Password needs to be re-entered for security purposes.

ONLINE ACTIVATION STEPS


WINDOWS and MAC




IMPORTANT NOTICE:

Make sure the computer SpotOn! Flexo was installed on is connected to the internet and a **Product Key** is available to activate SpotOn!.


Step 1: *Launch **SpotOn! Flexo** and click the **Activate** button on the Activation window.*



Step 2: *Enter the **Product Key** and click **Activate**.*



Step 3: This window will appear if the activation is successful. *Click **Finish** to complete the activation process.*



OFFLINE ACTIVATION STEPS


WINDOWS and MAC




IMPORTANT NOTICE:

Offline activation is a two part process. It requires an **Activation Request** file be e-mailed to activation@spotonpress.com. A reply will be e-mailed back with an **Activation Response** file that will be used to finish the activation process. Make sure a **Product Key** is available to activate SpotOn!.


Step 1: *Launch SpotOn! Flexo and click the **Activate** button on the Activation window.*




Step 2: *Enter the **Product Key** and click **Activate**.*




Step 3: This window will appear if the computer is not connected to the internet. *Click **Activate Manually** to start the offline activation process.*




Step 4: Click **Create Request File** to save the SpotOn! Activation Request file.




Step 5: Click **Save** to save the SpotOn! Activation Request file where it can be copied to a another computer and emailed to *activation@spotonpress.com*. A reply will be emailed back with an **ActivationResponse.xml** file to finish the activation process.



Step 6: Copy the **ActivationResponse.xml** file to the SpotOn! Flexo computer and click **Activate from Response File** to continue the activation process.



Step 7: Find the **ActivationResponse.xml** file and click **Open**.



Contact Information

If you require technical support, please e-mail us at: support@spotonpress.com

US & Canada

Tel.: 503-226-7598

Fax: 503-226-7892

E-mail: support@spotonpress.com

Other Countries

Contact your local dealer